Number of SubVIs defined	4	Available in the functions palette
Number of controls defined	1	Available in the controls palette
Report generation version	v1.0.3.7	
Current revision number	2	
Last revision date	-	
Current revision date	27-02-2018	

SI. No	Error code	Error detail description	Solution
1	700001	Image filepath not provided / Image unavailable	Either provide the image directly as input or the image filepath as the input. The image input is a recommended input so that a filepath in which image is already stored can be provided alternatively.      If image is not provided provide the filepath for generating the report
2	700002	The image width and height must be greater than 20	1. Make sure that the image (in mm) and image height (in mm) is greater than 20 to ensure the proper
3	700003	Neither the image nor the image filepath is provided at the input	Neither the image nor the image filepath is provided at the input. Ensure that atleast one of the above is provided
4	700004	The image save filepath doesn't exist	Please verify that the filepath "C:\Program Files (x86)\National Instruments\LabVIEW 2015\vi.lib\Zentron Labs Pvt Ltd\ZenReport\Buffer files\Display image" exists
5	700005	Report TEX template(s) or batch files are missing in Generate Report VI	Please verify that the filepath of the following files:  1. C:\Program Files (x86)\National Instruments\LabVIEW 2015\vi.lib\Zentron Labs Pvt Ltd\ZenReport\Source files\Templates\Report template.tex 2. C:\Program Files (x86)\National Instruments\LabVIEW 2015\vi.lib\Zentron Labs Pvt Ltd\ZenReport\Source files\Templates\PDF_convert_template.bat 3. C:\Program Files (x86)\National Instruments\LabVIEW 2015\vi.lib\Zentron Labs Pvt Ltd\ZenReport\Source files\Templates\PDF_convert.bat 4. C:\Program Files (x86)\National Instruments\LabVIEW 2015\vi.lib\Zentron Labs Pvt Ltd\ZenReport\Source files\Templates\PDF_convert.bat If not please report to the developer
6	700006	One or more bookmarks are missing in the Tex template.	Verify that the bookmarks mentioned in the dynamic inputs are available in the Tex template

	7	700007	Certain characters are not permitted in Batch or part names : "-"	Give a name without the special characters specified
I	8	700008	Invalid report type in the configuration	Give the correct name for the report type in the configuration [Part / Batch]